

Permission	Description	Example Viewer Only Role	Example Dispatch Role	Example Basic Role Patrol	Example Basic Plus Role Investigator	Example Enhanced Role Specialized Unit/RTCC	Example Supervisor Role (Operational Dashboards, ALPR entries)	Example Command Staff Role (lieutenant and higher)	ADMIN
The following example roles are only inclusive of permissions and would then be linked to specific camera/location/layer permissions.									
Administrator: Organization	Granted all organization permissions, and is able to manipulate organization settings								X
Alarm Admin	Allows the user to close out an alert prior to the automated 24hr setting and also view previously closed alerts.			X	X	X	X	X	
Alarm Viewer	Allows the user to receive alerts (i.e., Gun Shot Detection, ALPR, GPS Trackers, etc.).			X	X	X	X	X	
Auditor	Allows the user to view, filter, and export audit reports							X	
Axon User	Feature In Development/Not yet released.								
Chat Admin	Allows the user to create, send, receive, rename, change Public/Private, modify users and from an existing Public channel or any Private channel they are a member. and delete an existing Public channel or Private channel they are a member of. Must have Map Viewer Permission to access chat.								
Chat User	Allows the user to create, send, receive, and set Public/Private ONLY for the initial chat created by the user. Must have Map Viewer Permission to access chat.			X	X	X	X	X	
Connect User	Permits use of the fūsusConnect application. Should be given to any fūsusConnect user. This is an external application for key infrastructure locations and not needed for internal agency users.								
Dashboard Admin	Allows the user to create, edit (Add or remove widgets, resize or reorder), set Public/Private, and delete Operational Dashboards.						X		
Dashboard Viewer	Allows the user to see Public Operational Dashboards.			X	X	X	X	X	
Evidence.com Uploader	Allows the user the ability to export from fūsusVault to Evidence.com.								
Grids Admin	Allows the user to create, edit, set Public/Private, and delete Grids. Provides access to externally share an Organization Grid.			X	X	X	X	X	
Grids Viewer	Allows the user to select cameras and send them to a grid. Only saved in Temporary (24h) and cannot edit. Can view all Grids Admin-created Public Organization Grids.	X	X	X	X	X	X	X	
Layer Admin	This is a legacy permission (legacy customers must also have Map Viewer) previously used to hide specific layers. Please use the Layer Policy within the Permission Group settings to allow/restrict layers.			X	X	X	X	X	
Location and Camera Admin	Allows the user to add, delete, and edit cameras and locations, including position and orientation. Provides access to the user to set up location and camera sharing with other organizations.								
Location and Camera Viewer	Allows the user to view locations and cameras via the Navbar or on the map when paired with Map Viewer/Admin. Must select either Location and Camera Viewer or Location and Camera Viewer: RESTRICTED, NOT BOTH.	X	X	X	X	X	X	X	
LPR Admin	Provides access to the LPR search tool and provides access to manage internal hotlists.						X		
LPR Viewer	Provides user access to the LPR search tool.			X	X	X	X	X	
Map Admin	Dock cameras, create clips, create incidents, or utilize any other Map-accessed feature				X	X	X	X	
Map Panorama Admin	Allows the user to upload Panoramic images.								
Map Viewer	Dock cameras, create clips, create incidents, or utilize any other Map-accessed feature.	X	X	X	X	X	X	X	
Mutual Aid Admin	Feature In Development/Not yet released.								
Notify Admin	Allows the user to send fūsusNotify messages.								
Offender Viewer	Allows the user to view Offender layers		X	X	X	X	X	X	
Ops User	Allows the user to use the fūsusOPS Mobile Application.			X	X	X	X	X	
PTZ Controller	Allows the user to access PTZ camera controls. Must have Location and Camera Viewer.				X	X	X	X	
Registry Admin	Allows the user to add, delete, and edit fūsusREGISTRY participants.								
Registry Viewer	Allows access to fūsusREGISTRY information and ability to send fūsusRegistry requests.								
Restricted Location and Camera Viewer	View all locations and cameras via only the respective Navbar functions, not via the Map but not able to upload to Vault			X	X	X	X	X	
User Management Admin	Allows the user to add, delete, and edit users. Allows the user to create and modify Teams and Permission Groups.								
User Management Viewer	Allows the user to view the users' list via the Navbar.						X	X	
Vault Admin	Allows the user to edit, download, share, and delete fūsusVault files.								
Vault Viewer	Allows the user to access and view files in the fūsusVault.					X	X	X	
Video Room Admin	Allows access to initiate LiveLink. Can delete Livelink rooms, and remove participants from rooms and recordings.						X		
Video Room User	Allows access to initiate LiveLink.		X			X	X		
Video Wall User	Prevents cloud-connected streams from timing out; Only for use by RTCC personnel. This permission is limited, consult your PM/CSM. This permission is not inherited via the Organization Administrator's Permission.	X	X						